

# **E-Track Application**

Makson Healthcare Pvt. Ltd.

Software Requirement Specification (SRS)

The document details the summary of solution architecture and approach for the development of E-Track for Makson Healthcare Pvt. Ltd(MHPL). The document is based on the inputs, system study, discussions and meeting held between BCI & Makson Healthcare Pvt. Ltd (MHPL) Pvt Ltd (MHPL). This track & trace system should be implemented as per Makson (MHPL), P&G and DGFT guidelines as per requirements.

PO NO

MHPL|HYD|CAP|23-24|016

MHPL|HYD|CAP|23-24|017

Prepared By: Leena

Submission Date: 1-Sept-2023

Version: 1.2.0

# REVISION HISTORY

REVISION NO.	DATE	PREPARED BY	REVIEWED BY	COMMENT
1.0.0	09-08-2023	Prateeksha, Leena	Chandrakant Shindkar	Software Requirement Specification document for Makson Healthcare Pvt. Ltd. for DGFT eTrack Application.
1.1.0	23-08-2023	Leena	Santosh Parekh	Annexure of line barcode details is added.
1.2.0	01-09-2023	Leena	Chandrakant Shindkar, Santosh Parekh	Incorporated changes as per Makson Healthcare Pvt. Ltd. team comments

## Abbreviations:

Client: Makson Healthcare Pvt. Ltd., henceforth will be referred as Makson Healthcare Pvt Ltd (MHPL).

**Vendor:** Bar Code India, henceforth, will be referred as BCI.

#### NOTICE:

This document contains information, which is the proprietary property of Bar Code India. This document is received in confidence and its contents cannot be disclosed or copied without the prior written consent of Bar Code India.

Nothing in this document constitutes a guaranty, warranty, or license, express or implied. Bar Code India disclaims all liability for all such guaranties, warranties, and licenses, including but not limited to: Fitness for a particular purpose; merchantability; not infringement of intellectual property or other rights of any third party or of Bar Code India; indemnity; and all others. The reader is advised that third parties can have intellectual property rights that can be relevant to this document and the technologies discussed herein and are advised to seek the advice of competent legal counsel, without obligation of Bar Code India.

The changes should be mutually agreed and cancellation rights should have both the ends. Bar Code India makes no warranty for the use of this document and assumes no responsibility for any errors that can appear in the document nor does it make a commitment to update the information contained herein.

#### **COPYRIGHT**

Copyright © BCI 2023. All rights reserved.

#### **TRADEMARKS**

\*Other product and corporate names may be trademarks of other companies and are used only for explanation and to the owners' benefit, without intent to infringe.

# Table of Contents

1	:	Speci	tication Organization	1
2	ı	Introd	duction	2
	2.1	1	Intended Audience and Reading Suggestions	2
	2.2	2	Project Scope	3
3	ı	User	Interface Specification Conventions	4
4	9	Syste	m Log	5
	4.1	1	Error Logs	5
5	,	Appli	cation Modules- Web, Desktop & Device	6
	5.1	1	Application Login	6
	5.2	2	Menu	8
	5.3	3	User Management & Master Data	9
	į	5.3.1	User Master	9
	į	5.3.2	Reset Password	11
	į	5.3.3	Change Password	11
	į	5.3.4	Company Master	11
	į	5.3.5	Plant Master	12
	į	5.3.6	GTIN Master	14
	į	5.3.7	Line Master	15
	į	5.3.8	Consignee Master	16
	!	5.3.9	Printer Master	18
	١	5.3.10	0 Label Design Master	19
6	-	Trans	actions	21
	6.1	1	Batch Creation	21
	(	6.1.1	Serial Number Generation	22
	(	6.1.2	Label Printing	23
	(	6.1.3	Job Creation	24
	(	6.1.4	Scanning	26
	(	6.1.5	Rejection	27
7	ı	Repo	rts	29
8	,	Anne	xure	30
9	9	SRS S	cope Change Process	37
	9.1	1	Before Sign Off	37
	9.2	2	After Sign Off	37
	9.3	3	SRS Acceptance	37

# 1 SPECIFICATION ORGANIZATION

The objective of this document is to supply underlying concepts, procedures, and formats used in the design, development and installation of this software application. This specification consists of three sections organized as follows:

#### **Section 1: Introduction**

This section provides hardware requirements and documentation conventions.

#### Section 2: User Interface

This section depicts screen design and logic flow, and is categorized into two groups:

- Application Function Module
- Common Routine

## **Section 3: System Architecture**

This section provides information of system architecture.

Specifications:

**Hardware Requirements** 

The following are the minimum hardware requirements for your Track & Trace System. In a testing as well as production environment, the volume of traffic may dictate greater hardware requirements for your servers.

Component	Minimum Requirement
Processor	Minimum: Intel Xeon Processor 3.1 GHz Recommended: Intel Xeon Processor 3.1 GHz or faster
Memory	Minimum: 16 GB RAM
	Recommended: 16 GB RAM or Later
Available Disk	Minimum: 100 GB
Space	Recommended: 500 GB or Greater
DB Backup	Minimum: daily database backup by customer IT team.
	Recommended: daily or weekly database backup by customer IT team.



# 2 Introduction

## 2.1 Intended Audience and Reading Suggestions

The scope of this document is to provide the understanding of this solution to user & development teams associated with the application development & implementation.

This document major emphasizes on providing clear understanding of e-Track Application.

This solution comprises of:

- Device Application
- Desktop Application
- ERP Integration (API Interface)

#### Hardware:

- CIJ Printer
- P&A Machine
- Barcode Scanner
- Barcode Printer



# 2.2 PROJECT SCOPE

The e-Track application implements the persistent data requirement for management of packaging Serialization System in compliance with 21 CFR Part 11 requirements and Serialization guidelines of DGFT India.

This would require development of **Wi-Fi enabled application for real time transaction** i.e. the data will be captured in real-time, once the data has been collected, the database can then provide useful reports about status of material production area.



# 3 USER INTERFACE SPECIFICATION CONVENTIONS

This section specifies the user interface portion of the application.

#### **Section Organization**

The User Interface Specification presents screen displays or "Dialogs".

#### **Documentation Conventions**

This section incorporates illustrations of the application user interface. Each screen display "Dialog" consists of the screen display image, a process name, a paragraph documenting the processing required for the dialog, a paragraph listing the navigation options, and a table listing for each variable field on the dialog, its database source or destination, format, and any instructions required to process the field.

The following section contains a sample dialog with each area identified.



# 4 SYSTEM LOG

System shall maintain internal logs for application.

# 4.1 ERROR LOGS


These logs will contain any errors encountered during runtime for faster resolution of any problem post deployment.



# 5 APPLICATION MODULES- WEB, DESKTOP & DEVICE

## 5.1 Application Login

This login module will provide access to the application modules. Here the admin/user needs to enter the login detail to enter in the application and to perform the desired actions.



**Process:** User needs to enter the User Name/ID and Password in display fields and press the Login button. Application will validate the user credential.

User will be able to view only those screens/ modules of which he has been given access rights to.

#### **Validation**

- User Name/ID will be unique for all users.
- User Name/ ID and Password length will be set.
- After 3 unsuccessful login user has to reset the password.

To check the steps refer 5.3.2 section.

After successful login application menu screen will appear. Menu screen will have the Master, Label Printing, DB Settings and Reports options etc.



## **Login Sample Screen:**





# **5.2** MENU



### The menu consist of:

- Batch Creation
- Generation
- Printing
- Job Creation
- Scanning
- Rejection
- Reports



# 5.3 USER MANAGEMENT & MASTER DATA

The module will let application administrator to manage the Users, and the rights assigned to the same; the rights will define authorized application access of users.


### 5.3.1 USER MASTER

The module will be used to add, save, delete a particular user details. Admin user will enter details of application's user. The users will be provided with unique id and password through which they will be able to login to the system. Using this module, admin will provide the access rights of the required application modules to user.

Data Fields	1. Plant Code
	2. Department Name
	3. User Id
	4. User Name
	5. Employee Code
	6. Email Id
	7. User Status
	8. Remark
	9. Rights
Process Steps	Select Plant Code from dropdown.
	2. Select Department Name from dropdown.
	3. Enter User Id, Username, Employee Code, Email Id and Remark.
	*User Name and Password should be equal to or greater than eight characters.
	4. Select User Type from dropdown.
	5. Select Modules for which Access rights needs to be assigned to user.
	*By default admin get rights of all modules and for users, admin can decide for which
	modules/rights should be accessible to particular users.
	6. Save and Update the details in database.
	7. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd.
	requirement.

#### **Sample Screen:**







#### **5.3.2** Reset Password

# Process Steps 1.

- 1. User enter the invalid login credentials for 3 times.
- 2. User is deactivated.
- 3. User inform the admin for activation.
- 4. Admin login on application with his credentials.
- 5. Admin click on grid and select the deactivated user.
- 6. Admin activate the user.
- 7. Enter the User credentials set by admin.
- 8. Reset password screen will be displayed.
- 9. User will enter the new and confirm password.

### 5.3.3 CHANGE PASSWORD

#### **Process Steps**

- 1. User will click on change password.
- 2. Enter old password and new password in respective fields.
- 3. Click on confirm password button.
- 4. The password will be changed.
- 5. Click on login.
- 6. Enter new password for login.

### 5.3.4 COMPANY MASTER

The master module will be used to save the Company details against in database.

#### **Data Fields**

- 1. GS1 Prefix (BCI will create 4 instances of company prefix as confirmed by Makson
  - Healthcare Pvt. Ltd)
- 2. Company Name
- 3. Company Address 1
- 4. Company Address 2
- 5. City
- 6. State
- 7. Country
- 8. Pincode
- 9. Status i.e. Active/ Inactive


#### **Process Steps**

1. Enter GS1 Prefix, Company Name, City, State and other details.



	2. Select Active/ Inactive Status.
	3. Save details.
	4. Newly added Company details will appear on screen in data grid.
	5. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd
	requirement.

### Sample Screen:



# 5.3.5 PLANT MASTER


The master module will be used to save the Plant details against in database.

Data Fields	1.	Company (GS1 Prefix) (Dropdown for selection)
	2.	Plant Code
	3.	Plant Name
	4.	Plant Address 1
	5.	Plant Address 2
	6.	City
	7.	State
	8.	Country
	9.	Pincode
	10.	Plant Type



	11. Remarks
	12. Status i.e. Active/ Inactive
Process Steps	Select Company (GS1 Prefix) from dropdown.
	2. Enter Plant Code, Plant Name, Plant Address 1, Plant Address 2, City, State and other
	details.
	3. Save the details.
	4. Newly added Plant details will appear on screen in data grid.
	5. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd
	requirement.

### Sample Screen:






# 5.3.6 GTIN MASTER

This master will be used to view the GTIN details in database. Using this module, user will be able to add, update and delete as per requirement.

Data Fields	1. Company Prefix
	2. Packing Level
	3. GTIN Code
	4. Generate GTIN Code
	5. ERP Item Code
	6. Product Description
	7. Quantity in Box
	8. Pack Size
	9. Label Design ID
	10. Customer ID
	11. Expiry Period
	12. Status
	13. Generic Name
	14. Composition
	15. Schedule
	16. Usage
	17. Art Work
	18. Remark
Process Steps	1. Click on Add button.
	2. Select Company Prefix, Packing Level, Label Design ID, Customer ID.
	3. Enter GTIN Code, Generate GTIN Code, ERP Item Code, Product Description, Quantity in
	Box, Pack Size, and other details.
	4. Click on Status button to activate it.
	5. Select Art Work file by clicking on Browse button.
	*Fields marked with * are mandatory.
	6. Click on Save.
	7. Newly added GTIN details will appear on screen in data grid.
	8. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd
	requirement.

## Sample Screen:





## 5.3.7 LINE MASTER


This module will allow user to Line details.

Data Fields	1. Company ID
	2. Plant ID
	3. Name
	4. Status
	5. Line Type
	6. Product Code
	7. Printing Method
	8. Label Type
	9. Scanning Method
	10. Scanning Device
	11. Port
	12. Device IP
	13. Com Port
	14. Print File Name
	15. Remark
Process Steps	1. Click on Add button.



	2. Select Company ID, Plant ID, Line Type, Printing Method, Label Type, Scanning Method
	from dropdown.
	3. Enter Name, Product Code, Scanning Device, Port, Device IP, and other details.
	4. Click on Status button to activate it.
	5. Click on Save.
	6. Newly added Line details will appear on screen in data grid.
	7. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd
	requirement.

### Sample Screen:



# 5.3.8 Consignee Master


This master will be used to view the Consignee details in database. Using this module, user will be able to add, update and delete as per requirement.

Data Fields	1.	Customer Name
	2.	Address
	3.	Address1
	4.	Address2



	5. City
	6. State
	7. Pincode
	8. Country
	9. Tertiary ID
	10. Secondary ID
	11. Status
Process Steps	1. Click on Add button.
	2. Enter Customer Name, Address, Address1, Address2, Country. and other details.
	3. Select Tertiary ID, Secondary ID from dropdown.
	4. Click on Status button to activate it.
	*Fields marked with * are mandatory.
	5. Click on Save.
	6. Newly added Consignee details will appear on screen in data grid.
	7. User can export the details in Excel format, if required.
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd
	requirement.

### Sample Screen:






# 5.3.9 Printer Master

This master will be used to view the Printer details in database. Using this module, user will be able to add, update and delete as per requirement.

Data Fields	1. Printer Name			
	2. Printer Type			
	3. Printer Model			
	4. Driver Model			
	5. IP Address			
	6. Port No			
	7. Line ID			
	8. Plant ID			
	9. Status			
Process Steps	1. Click on Add button			
	2. Enter Printer Name, Printer Type, Printer Model, Driver Model. and other details.			
	3. Select Line ID, Plant ID from dropdown.			
	4. Click on Status button to Activate it.			
	*Fields marked with * are mandatory.			
	5. Click on Save.			
	6. Newly added Printer details will appear on screen in data grid.			
	7. User can export the details in Excel format, if required.			
Functions	Add, Edit/Update, Deactivate and Export to Excel as per Makson Healthcare Pvt. Ltd			
	requirement.			

### Sample Screen:





# 5.3.10 Label Design Master


This master will save the EAN Code details in database.

Data Fields	1.	Packing Level
	2.	Label Type
	3.	Label Size
	4.	PRN Type
	5.	Plant ID
	6.	Line ID
	7.	Select PRN File
	8.	Status
Process Steps	1.	Click on Add button.
	2.	Select Packing Level, Label Type, Label Size, PRN Type, Plant ID, Line ID from dropdown.
	3.	Enter Label Size.
	4.	Click on Browse button to select PRN file
	5.	Click on Status button to Activate it.
		*Fields marked with * are mandatory.
	6.	Click on Save.
	7.	Newly added Label design details will appear on screen in data grid.
	8.	User can export the details in Excel format, if required.



	*The labels design are as per Makson Healthcare Pvt. Ltd data.	
Functions	Add, Edit/Update, Deactivate as per Makson Healthcare Pvt. Ltd requirement.	

#### **Sample Screen:**






# 6 Transactions

This application will Installed on Desktop Computer on packing line.

## 6.1 BATCH CREATION

- 1. The Batch Creation module is used to create/close batch on desktop computer on packing line.
- 2. To access this module, the User must select on Generation > Batch Creation menu. The Batch Creation screen will be displayed.




- 3. To Create a New Batch, the User should click on Add New Record.
- 4. The Plant Code and Company Prefix will be auto-displayed.
- 5. The User should then select the ERP Code. The corresponding the GTIN, Product, BCIL ID and Pack Size will be displayed.
- 6. The User will then update the Batch No, Unit price, Number of Primary Units and other batch related details.
- 7. To save the batch, Click on Save Batch Creation button to save batch.
- 8. To close an existing batch, the User should select batch from list which they wish to close and click on Close selected Batch(s) button.



#### 6.1.1 Serial Number Generation


- 1. Serial No Generation module is used to generate request for a serial no printing. The serial No request generation will be on desktop computer on packing line and the data will be generated on the server.
- 2. To access this module, the User should select Generation > Serial No Generation menu. The Serial No Generation screen will be displayed.



- 3. To generate request for printing, the User should select Plant Code, Packing Level, Label Type and Line Code in Line Selection.
- 4. The User should select product, GTIN and product related batch, ERP Code, Y\_Level from the list.
- 5. The User should enter the number of labels in Input Request qty and Pack Size.
- 6. To save the transaction, click on Save Generation Data Button.

### 6.1.2 LABEL PRINTING

- 1. Serial Number printing module is used to print labels.
- 2. To access this module, The User should click on Printing menu. The Serial Number Printing screen is displayed.





- 3. To Print Barcode Labels, the User should select Plant Code, Packing Level, and Line No in Line Selection.
- 4. After selecting Line, Label Type, Print Method and Label Size will get auto displayed for that line.
- 5. The User should then click on View Printing Requests Button. The generated request will be displayed for selected line.
- 6. The User should select any one record from list and enter No of labels qty (which they wish to print).
- 7. To print, click on print Button.



# 6.1.3 JOB CREATION

- 1. Mapping Job Creation module is used to Create Job against specific GTIN and batch for a packing process.
- 2. To access this module, User should click on Job Creation menu. The Job Creation screen will be displayed.





- 3. To create a new Job, click on Add New Record button.
- 4. Select Plant Code, Packing Level, Line Code in Line Selection.
- 5. The User should then select Product, GTIN and Batch No in Product Selection.



- 6. Enter Pack Size.
- 7. After selecting Values, the User should click on Create New Job Button and Job will be displayed.

### To Upload to Device (For Offline Scanning)

- 1. To perform the uploading process, the User should confirm if the device is connected.
- 2. The User should then select the Job from list which they wish to upload and click on Upload Button

#### **To Close Existing Jobs**


1. The User should select Job from list which they wish close and then click on **Close Job** Button



### 6.1.4 SCANNING

### 6.1.4.1 PARENT CHILD SCANNING (HOMOGENOUS)

- 1. Click on Mapping Scanning. The Mapping Scanning will be displayed.
- 2. If device is connected, then the User should select Packing level as a 'Tertiary', Line No from dropdown.




- 3. By default Homogeneous label type will get selected.
- 4. Select Batch No, Pack Size drop dropdown.
- 5. Print Configuration details will be displayed on the screens after selection of Line No.
- 6. Scan Child Barcode.
- 7. Child Barcode details will be displayed on the screen.
- 8. Scan count will be displayed on the screen.
- 9. When the Pack Size matched to scan count, the tertiary label will be printed.



# 6.1.5 REJECTION

### 6.1.5.1 GENERAL REQUEST REJECTION

- 1. Generation Request Rejection module is used to Reject Serial No generation request.
- 2. This module will be accessible on both client and server system.
- 3. To access this module, the User should click Rejection > Generation Request Rejection menu.




- 4. Select Plant Code, Packing Level, Line code from dropdown for Line Selection.
- 5. Select Product from dropdown for Product selection section.
- 6. Enter Batch No.
- 7. User can view requests in General Request section by clicking on View Requests. button.



#### 6.1.5.2 SERIAL NO REJECTION

- 1. Serial Number Rejection module is used to reject printed barcodes.
- 2. This module will be accessible on both client and server system.
- 3. To access this module, the User should click Rejection > Serial No Rejection.



- 4. For Serial No Rejection, the User should select Plant Code, Packing Level, and Line no in Line Selection.
- 5. The User should then select Product and Batch from Barcode Details.
- 6. After selecting Values, the User should click on View Serial No's/View Unused Barcodes Button and generated Barcodes will be displayed.
- 7. Then select Barcode from list and Click on Reject button.



# 7 REPORTS

- Tertiary Sumarised Report
- Secondary Summarised Report
- Unutilized Report Secondary
- Unutilized Report Tertiary
- Summary Report
- Wrong Packing Report
- Event Log Report

\*All data reports can be visible on server as well as client system.





# 8 ANNEXURE

# Line 1 – JAR LINE - PRINT & APPLY

	Example:		
		EXP.	14987176601381 DATE 10/2019 CH 6328038794JE H228226LYK
Lines	Structure	Format	Rule
Line 1	GTIN 14	(01) XXXXXXXXXXXXXX	(01) = Indicates the data following AI (01) is GTIN-14.  XXXXXXXXXXXXXXX = denotes GTIN-14 of the secondary  pack. GTIN starts with digit 1.
Line 2	Expiry date Human readable form (HRF)	EXP. DATE MM/YYYY	EXP. DATE = Expiry date  MM = 2 digit month of  expirationYYYY = 4 digit year of  expiration
	Part of QRcode only (will not be partof the HRF)	(17)YYMMDD	(17) = Indicates the data following AI (17) is the expirydate  YY = Last two digit of the year of expirationMM = 2 digit month of expiration  DD = 2 digit date of expiration (should be 00)
Line 3	Batch number HRF	BATCH YDDDPPPP\$\$XX	BATCH = Batch number Y = Last digit of manufacturing year DDD = Julian Day code of manufacturePPPP = Plant code \$\$\$ = Batch no. XX = SKU specific code (Refer to Section IV)
	Part of QRcode only (will not be partof the HRF)	(10)YDDDPPPP\$\$XX	(10) = Indicates the data following AI (10) is the batchno./ lot no. of the secondary package.  Y = last digit of the manufacturing yearDDD = Julian Day code of manufacture PPPP = Plant code  \$\$\$\$ = serial no. for the batch  XX = SKU specific code (Refer to Section IV -Specific code per SKU for Jars)



Line 4	Serial Number	(21) aaaaaaaa	(21) = Indicates the data following AI (21) is the
			serial
			no. of secondary package.
			aaaaaaaa = Serial number of the secondary pack. The
			number can be alphanumeric with maximum 20 digit
			long.
			The number should not be repeated and must
			remain
			unique for all secondary packs.

# <u>Line 2 – FLAT LINE – INKJET CODING</u>

	Example:			
(01)14987176800759 EXP. DATE 10/2018 BATCH6248038792FD (21)H421619LR6 MFG. DATE 11/2016				
Line 1	GTIN 14	Line 1: (01)XXXXXXXXXXXXXX	Line 1:  (01) = Indicates the data following AI (01) is GTIN- 14.XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX	
Line 2	Expiry date Human readable form (HRF)  Part of QR code only (will notbe part of the HRF)	EXP. DATE MM/YYYY  (17)YYMMDD	EXP. DATE = denotesexpiry date  MM = 2 digit month of expiration  YYYY = 4 digit year of expiration,  (17) = Indicates the data following AI(17) is the expirydate  YY = Last two digit of theyear of expiration,  MM = 2 digit month of expiration  DD = 2 digit date of expiration (should be 00)	
Line 3	Batch numberHRF	BATCH YDDDPPPP\$\$XX	BATCH = Denotes batchnumber Y = last digit of the Year, DDD = Julian Day code ofManufacture PPPP = Plant code, \$\$ = Batch no XX = SKU specific code (refer to table given at the end of PI- specific code persku for flats)	



	Part of QR code only (will notbe part of the HRF)	(10)YDDDPPPP\$\$XX	(10) = Indicates the data following AI (10) is the batchno./ lot no. of the secondarypackage Y = last digit of the Year DDD = Julian Day code of Manufacture PPPP = Plant code \$\$ = serial no. for the batchXX = SKU specific code (refer to table given at the end of PI- specific code persku for flats)
Line 4	Serial Number	(21)aaaaaaaa	(21) = Indicates the data following AI (21) is the serialno. of secondary package aaaaaaaa = Serial number of the secondary pack. The number can be alpha numeric with maximum 20 digit long. The number should not be repeated and remain unique for all secondary packs
Line 5	Manufa cturing date Human readable form only(HRF)	MFG. DATE MM/YYYY	MFG. DATE = denotesmanufacturing date MM = 2 digit month of manufacturing  YYYY = 4 digit year of manufacturing



# <u>Line 3 – INHALER-1 – INK JET CODING MACHINE</u>

### Example:



Lines	Structure	Format	Rule
Line 1	GTIN 14	(01)XXXXXXXXXXXXXXX	(01) = Indicates the data following AI (01) is GTIN-14.  XXXXXXXXXXXXXXX = denotes GTIN-14 of the secondary pack.GTIN starts with digit 1.
Line 2	Expiry date Human readable form(HRF)	EXP. DATE MM/YYYY	EXP.DATE= represents expiry date MM = 2 digit month of expirationYYYY = 4 digit year of expiration
	Part of QR code only (willnot be part of the HRF)	(17)YYMMDD	(17) = Indicates the data following AI (17) is the expiry dateYY = Last two digit of expiry year  MM = 2 digit month of expiration  DD = 2 digit date of expiration (should be 00)
Line 3	Batch number (HRF)	BATCH YDDDPPPP\$\$XX	BATCH = represents batch no.  Y = last digit of manufacturing year DDD = Julian Day code of manufacturePPPP = Plant code  \$\$ = serial no. for the batch.  XX = SKU specific code (refer to Section IV - SpecificCode per SKU)
	Part of QR code only (willnot be part of the HRF)	(10)YDDDPPPP\$\$XX	(10) = Indicates the data following AI (10) is the batch no./lot no.of the secondary package.  Y = last digit of manufacturing year DDD = Julian Day code of manufacturePPPP = Plant code  \$\$ = serial no. for the batch  XX = SKU specific code (refer to Section IV - SpecificCode per SKU)
Line 4	Serial Number	(21)aaaaaaaa	(21) = Indicates the data following AI (21) is the serial no. ofthe secondary package.  aaaaaaaa = Serial number of the secondary pack. The number can be alphanumeric with maximum 20 digits.  The number should not be repeated and must remain



	unique for all secondarypacks.

# Line 4 - INHALER-2 - INK JET CODING MACHINE

## Example:



Lines	Structure	Format	Rule
Line 1	GTIN 14	(01)XXXXXXXXXXXXXX	(01) = Indicates the data following AI (01) is GTIN-14.  XXXXXXXXXXXXXXX = denotes GTIN-14 of the secondary pack.GTIN starts with digit 1.
Line 2	Expiry date Human readable form(HRF)	EXP. DATE MM/YYYY	EXP.DATE= represents expiry date MM = 2 digit month of expirationYYYY = 4 digit year of expiration
	Part of QR code only (willnot be part of the HRF)	(17)YYMMDD	(17) = Indicates the data following AI (17) is the expiry dateYY = Last two digit of expiry year  MM = 2 digit month of expiration  DD = 2 digit date of expiration (should be 00)
Line 3	Batch number (HRF)	BATCH YDDDPPPP\$\$XX	BATCH = represents batch no.  Y = last digit of manufacturing year DDD = Julian Day code of manufacturePPPP = Plant code  \$\$ = serial no. for the batch.  XX = SKU specific code (refer to Section IV - SpecificCode per SKU)
	Part of QR code only (willnot be part of the HRF)	(10)YDDDPPPP\$\$XX	(10) = Indicates the data following AI (10) is the batch no./lot no.of the secondary package.  Y = last digit of manufacturing year DDD = Julian Day code of manufacturePPPP = Plant code  \$\$ = serial no. for the batch  XX = SKU specific code (refer to Section IV - SpecificCode per SKU)

Line 4	Serial	(21)aaaaaaaa	(21) = Indicates the data following AI (21) is the
	Number		serial no. ofthe secondary package.
			aaaaaaaa= Serial number of the secondary pack. The
			number can be alphanumeric with maximum 20 digits.
			The number should not be repeated and must remain
			unique for all secondarypacks.

# <u>Line 5 – TUBE line – INK JET CODING MACHINE</u>

### Example:



Lines	Structure	Format	Rule
Line 1	GTIN 14	(01)XXXXXXXXXXXXXXX	(01) = Indicates the data following AI (01) is GTIN-14.
			XXXXXXXXXXXXX = denotes GTIN-14 of the secondary
			pack.GTIN starts with digit 1.
Line 2	Human	Exp. Date MM/YYYY	Exp. Date= denotes expiry date
	readable		MM = 2 digit month of
	form (HRF)		expirationYYYY= Year of
			expiration
	Part of QR	(17)YYMMDD	(17)= Indicates the data following AI(17) is the expiry
	code only		date
	(willnot be		YY= Last two digit of the year of expirationMM = 2 digit
	part of the		month of expiration
	HRF)		DD = 2 digit date of expiration
Line 3	Batch	Batch BBYM1XX	Batch= Denotes batch number
	number		BB = Batch sequence number in the monthY = Last digit
	(HRF)		of the year of Manufacturing M= Month of bulk
			manufacturing (Follow site SOP for the code of month
			to be used.
			E.g Y= Jan , E= Feb)1 = Fixed digit
	_		XX= specific sku code (TA is fixed specificsku code
	Part of QR		for VVR 80g tube)
	code only	()	
	(willnot be	(10)BBYM1XX	(10)= Indicates the data following AI (10) isthe batch
	part of the		no./ lot no. of the secondary package
			110./ 10t 110. Of the secondary package



### **SOFTWARE REQUIREMENT SPECIFICATION | 2023**

	HRF)		BB = Batch sequence number in the monthY = Last digit
			of the year of Manufacturing M= Month of bulk
			manufacturing (Follow site SOP for the code of month
			to be used.
			E.g Y= Jan , E= Feb)1 = Fixed digit
			XX= specific sku code (TA is fixed specificsku code
			for VVR 80g tube)
Line 4	Serial	(21)aaaaaaaa	(21)= Indicates the data following AI (21) is the serial no.
	Number		of secondary package aaaaaaaa= Serial number of the
			secondary pack. The number can be alpha numeric with
			maximum 20 digit long. The number should not be
			repeated and remain unique for all secondary packs



# 9 SRS Scope Change Process

## 9.1 Before Sign Off

Any changes in SRS need to be informed in writing by Makson Healthcare Pvt. Ltd. It will be incorporated / confirmed only after doing detailed feasibility study by BCI.

- If any change is out of scope then this would be done as a CR post feasibility and priority will be decided based on mutual agreement.
- Once the change is developed, any further change in the same would be considered as a CR

### 9.2 AFTER SIGN OFF

Any changes in proposed solution after approval of this document by Makson Healthcare Pvt. Ltd (MHPL) are subjected to confirmation from BCI, taking feasibility constraints into account. These changes will be incorporated (if any) into the solution only after delivering proposed solution & may be charged as extra.

- Any change in the proposed solution due to customer system design or process will be considered as CR
- Any process which is not mentioned in this document will not be considered as "mutual understanding or default presence or standard practice".

The changes in proposed solution before & after acceptance will be mutually agreed and duly signed and accepted by Makson Healthcare Pvt. Ltd (MHPL) & BCI.

For Bar Code India (BCI)

### 9.3 SRS ACCEPTANCE

For Makson Healthcare Pvt Ltd (MHPL)

Agreed and Accepted by Makson Healthcare Pvt. Ltd (MHPL) and Bar Code India

Name:	Name:
Designation:	Designation:
Department:	Department:

